
CentreStack File Server Agent Documentation

Release 9.7.5645.41666

Gladinet, Inc.

May 04, 2023

Contents

1	1 Introduction	3
1.1	1.1 Background	3
1.1.1	1.1.1 Security or Mobility?	3
1.1.2	1.1.2 Security + Mobility	4
1.1.3	1.1.3 Overview	4
1.1.4	1.1.4 As a Summary	4
1.1.5	1.1.5 How it solves the problem?	5
1.1.6	1.1.6 What is a typical way to use File Server Agent?	5
2	2 Installation	7
2.1	2.1 System Requirement	7
2.2	2.2 Preparation	7
2.3	2.3 Install	9
2.3.1	2.3.1 Step 1 - Download the Installer Package	9
2.3.2	2.3.2 Step 2 - Run the Installer Package	11
2.3.3	2.3.3 Step 3 - Welcome Screen	11
2.3.4	2.3.4 Step 4 - License Agreement	11
2.3.5	2.3.5 Step 5 - Confirm Installation	15
2.3.6	2.3.6 Step 6 - Installation is Finishing	15
2.3.7	2.3.7 Step 7 - Installation Complete	15
2.3.8	2.3.8 Step 8 - Restart Your System	15
2.3.9	2.3.9 Step 9 - Login To CentreStack	15
3	3 Administration and Configuration	19
3.1	3.1 File Server Agent Components	19
3.2	3.2 Cloud Server Console - Web View	20
3.2.1	3.2.1 Device Info	24
3.2.2	3.2.2 CIFS Shares	24
3.2.2.1	3.2.2.1 Migrate	27
3.2.3	3.2.3 Attached Folders	27
3.2.3.1	3.2.3.1 How to Attach a Folder	27
3.2.3.2	3.2.3.2 Filter Button	30
3.2.3.3	3.2.3.3 Diagnostic Button	30
3.2.3.4	3.2.3.4 Stop-Sync Button	31
3.2.3.5	3.2.3.5 Offline Folders	31
3.2.3.6	3.2.3.6 Local File Lock	33
3.2.3.7	3.2.3.7 Locked Files	33

3.2.3.8	Pending Check-ins	34
3.2.4	3.2.4 Settings	34
3.2.5	3.2.5 Task Manager	34
3.2.6	3.2.6 Migrate CIFS SHARES	34
3.2.7	3.2.7 Migrate Users	34
3.3	3.3 Cloud Server Console - Native	34
3.3.1	3.3.1 Task Manager	37
3.3.1.1	System Related Tasks	43
3.3.1.2	System Sync Task	43
3.3.1.3	System Sync Down Task	43
3.3.1.4	System Update Task	43
3.3.1.5	Edit Account Information	45
3.3.2	3.3.2 File Server	45
3.3.3	3.3.3 Attach/Backup	52
3.3.3.1	Link to Local Folder	57
3.3.3.2	Stop Sync	57
3.3.3.3	Detach	57
3.3.4	3.3.4 Audit Trace	57
3.3.5	3.3.5 Settings Manager	57
3.3.5.1	Offline Folders	57
3.3.5.2	Settings Tab	60
3.3.5.3	Bandwidth Control	60
3.3.5.4	Cache	60
3.3.5.5	Sync Control	62
3.3.5.6	Advanced	62
3.3.5.7	Trace	64
4	4 Advanced Topics	65
4.1	4.1 Migration Users	65
4.2	4.2 Migrate File Server Network or CIFS Share to CentreStack	65
4.3	4.3 Conclusion	65
5	Indices and tables	67

Contents:

CHAPTER 1

1 Introduction

CentreStack File Server Agent is a client agent software that runs on Windows machines and connect network shares on the Windows machine to CentreStack.

It is a file server enablement to allow remote and mobile access, while at the same time, provide business continuity through file synchronization and version control.

It is also a hybrid cloud setup that allows files and folders to be accessed from both local area network (file server map drive) and from remote locations/Cloud/Internet (via virtual mapped drive).

This is CentreStack File Server Agent Administration Guide.

Note: **File Server Agent** version 9.7.2576 or later

1.1 1.1 Background

1.1.1 Security or Mobility?

Businesses need ways to access local file server over the Internet from mobile devices and remote locations for productivity gain. This trend is pushing local file server content outward towards public file-sharing services such as Dropbox and OneDrive. Employees are using 3rd-party file-sharing services on their own to improve productivity.

Security and control is a big concern for businesses that are sensitive to regulation and data leakage problems. The lack of granular permissions and control over file sharing in public file-sharing services is forcing companies to give up on these 3rd-party services.

They then revert to the use of virtual private networks (VPNs) to provide remote access to corporate data. However, VPN has its own problems; it is not a good fit for the modern mobility, nor is it productivity friendly. Most of the time, VPN is a headache for managed service providers and company IT department, for the number of VPN related support tickets.

1.1.2 Security + Mobility

This is why you need CentreStack; resolving issues between file-sharing requirements, mobility and remote access, while preventing the leakage of your critical data through security and control. CentreStack takes care of the following objectives:

- Make the Windows file server mobility and remote-access friendly
- Maintain file-server accessing paradigm for local and remote access
 - Provide NTFS security permissions
 - Allow Active Directory integration
 - Drive Mapping and on-demand access
- File sync and share features integrated into a traditional Windows file server network share

1.1.3 Overview

CentreStack is the overall solution, and the File Server Agent client application is software that connects file servers to the CentreStack file-sharing solution.

The CentreStack File Server Agent is client-agent software that runs on Windows machines as a background service, while connecting to CentreStack servers (typically setup in a data center away from the file server).

File Server Agent allows you to turn your file servers into cloud-friendly servers to migrate the file server shares to the CentreStack environment, while maintaining the two-way synchronization for as long as you need it to be. During this process, the existing share permissions are also migrated to CentreStack. This allows the Windows file server network share to be used locally without change, and at the same time, the network shares are synchronizing with CentreStack Server to form a Hybrid Cloud solution.

File Server Agent technology turns any Windows file server into a private cloud storage that can be accessed from anywhere using any device, while maintaining existing identities and permissions.

1.1.4 As a Summary

1. File Server Agent can sync folders and files between the local file server and the remote CentreStack Server.
2. File Server Agent can sync NTFS folder permissions from a local file server to the remote CentreStack Server.
3. File Server Agent can export users to the remote CentreStack Server from a user's local Active Directory.
4. File Server Agent activity runs as a Windows background service on the local file server.
5. Users use their local Active Directory identity to access files locally and from the CentreStack Server.

Note: When should you use File Server Agent to connect your file server to CentreStack?

When should you use a direct server message block (SMB) network share connection?

Typically, when a file server is away not in the same data center or network, we recommend using Server Agent. (e.g. there is no physical connection between CentreStack and the “Server Agent” target system)

For file servers in the same data center, but in a different VLAN, we recommend opening up the VLAN so the CentreStack can direct access the file server without using a Server Agent since both are already in the same data center.




Fig. 1: CentreStack ACCESS FROM LOCAL FILE SERVER

1.1.5 How it solves the problem?

1. You or your managed service provider (MSP) owns the CentreStack software. File data is either located on the local file server or the CentreStack Server. Either way, you control the data to prevent unauthorized access.
2. CentreStack Server is operating from a data center or local office, behind a firewall connected to the Internet. Typical SMB protocol shares are not available to the Internet; however, the HTTPS communication (Internet facing) capability of the CentreStack Server makes it friendly to mobile and remote devices.
3. CentreStack Server either directly leverages the local Active Directory and NTFS permission or replicates these features to maintain a local-file-server access paradigm.

1.1.6 What is a typical way to use File Server Agent?

When your client needs to store files in local-network shared folders, Server Agent can be helpful for connecting these shares to CentreStack. This typically happens when there is a lot of users in the local office, or the Internet speed is ok but not great coming into the office.

One typical use case is you have remote workers or a branch office that have need to access the file server network share without using the VPN. You don't want to copy the file server content out just for the remote workers because that will create too many copies and lost track of which side has the newer version. Setting it up in a hybrid mode, and with two-way synchronization between local file server and remote CentreStack Server is a better way to go.

You can download and install the File Server Agent software directly from the Web Portal. Complete the following steps to install the CentreStack File Server Agent software on your file server.

2.1 2.1 System Requirement

File Server Agent can be installed on the following OS

- Server OS
 - Windows 2022
 - Windows 2019
 - Windows 2016
- Client OS
 - Windows 10
 - Windows 8.1
 - Windows 8.0
 - Windows 7
 - Windows Vista
 - Windows XP

2.2 2.2 Preparation

File Server Agent depends on .NET framework 2.0 or later. If you are installing the file Server Agent on Windows Server 2022/2019/2016, you need to prepare the .NET environment. This usually can be done from the Windows Server Manager > Manage Roles and Features and then in the features section, select .NET Framework 3.5




Fig. 1: WINDOWS SERVER 2016 .NET FRAMEWORK FEATURE

If you are installing File Server Agent on Windows 8/Windows 10, you can get .NET framework 2.0 (3.5) installed from “Program Files” -> Windows Components.




Fig. 2: WINDOWS 10 .NET FRAMEWORK 3.5 FEATURE

2.3 2.3 Install

Important: Always install CentreStack File Server Agent as a Tenant Administrator when you are at the login dialog. File Server Agent belongs to a specific Tenant instead of belonging to a specific user. So it is best to download the File Server Agent as the Tenant Administrator and set it up to connect to the same Tenant Administrator’s account.

2.3.1 Step 1 - Download the Installer Package

From the File Server you wish to install the File Server Agent; open a browser and log in to the Web Portal as the Tenant Administrator. From the Management Console, click the (+) in the “Remote Active Directory” section on the right-hand side.

In the pop-up window, choose your Download Package from the pull-down menu and click **Go** to begin the installation. A window will open. Click the MSI file at the bottom of the browser to open the installer.




Fig. 3: SERVER AGENT DOWNLOADS ACCESS




Fig. 4: OPEN THE INSTALLER

Note: File Server agent software is capable of synchronizing three things between the local file server and remote cloud storage account.

1. synchronize selected files and folders.
2. synchronize selected Active Directory users from local to cloud.
3. synchronize NTFS permissions on the local file server to cloud.

You can start installing file server agent from “Adding Remote Active Directory” or from “Adding Team Folder via Remote Server Agent”.

2.3.2 Step 2 - Run the Installer Package

Click **“Run”** to start the installation.

2.3.3 Step 3 - Welcome Screen

On the Welcome Screen choose **“Next”** to continue.

On the Welcome Screen choose **“Next”** to continue.

2.3.4 Step 4 - License Agreement

Read and accept the license agreement by choosing **“I Agree”** and click the **“Next”** button.




Fig. 5: RUN THE SERVER AGENT INSTALLER



Fig. 6: WELCOME SCREEN




Fig. 7: ACCEPT LICENSE AGREEMENT

2.3.5 Step 5 - Confirm Installation

Now we will complete the File Server Agent installation. Click **“Next”** to finish.




Fig. 8: CONFIRM INSTALLATION

2.3.6 Step 6 - Installation is Finishing

It will only take a few minutes to complete the installation.

2.3.7 Step 7 - Installation Complete

Once the installation is completed, click the **“Close”** button to finish.

2.3.8 Step 8 - Restart Your System

Just restart your system and File Server Agent is ready to use.

2.3.9 Step 9 - Login To CentreStack

After the reboot, log back into Windows as the same Windows user. Be patient, as it will take a few minutes for the Login Panel to display. Login to CentreStack as using your Tenant Administrator credentials.




Fig. 9: FINAL INSTALLATION PROCESS




Fig. 10: CLOSE INSTALLATION WINDOW





Fig. 11: RESTART YOUR SYSTEM

Note: The File Server Agent can be logged in to the Tenant already if you don't see the login dialog. You can go to the Web Portal side, login as the Tenant Administrator and go to the "Device Manager" side to see the File Server Agent.



The image shows a dialog box titled "Configure ACME Systems Account". It has a blue header bar with a cloud icon on the left. The main area is white and contains three text input fields. The first field is labeled "User Name (Email):" and contains the text "acmeadmin@mailinator.com". The second field is labeled "Password:" and contains a series of dots. The third field is labeled "Access Point (http://myhost.com):" and contains the text "http://10.0.0.221". Below the third field is a blue link labeled "Proxy Setup". At the bottom right of the dialog are two buttons: "Ok" and "Cancel".

Configure ACME Systems Account

User Name (Email):
acmeadmin@mailinator.com

Password:
.....

Access Point (http://myhost.com):
http://10.0.0.221

[Proxy Setup](#)

Ok Cancel

Fig. 12: LOG IN AS TENANT ADMIN

3 Administration and Configuration

CentreStack File Server Agent runs as a Windows Service in the background. Since it is a background service, it always runs regardless of the users logging into the server.

The administration of the File Server Agent is done via a Windows application (the Cloud Server Console). Most of the time, the Cloud Server Console will launch into the web browser based administration console.

There are two consoles, one on the Web Portal and the other one runs natively on a local machine. The one on the Web Portal is for general administration such as managing settings. The native console is for advanced troubleshooting such as collecting audit traces.

You need to log into the Windows server's console to use the CentreStack Server Agent Management Console for administration-related tasks. If you manage the Windows Server from remote locations, you can use Remote Desktop, or other remote control tools to access to the Windows server before you start the CentreStack Server Agent Management Console.

3.1 3.1 File Server Agent Components

There are 3 windows services and 1 windows Application

- Cloud Access Service (gladgroupsvc.exe) - This is the main sync service
- File Monitor Service (GladFileMonSvc) - This is responsible for Server Agent auto upgrade
- File System Mounter (gladmountsvc) - This is mount the Cloud File System for the Gateway mode
- Management Console (GtaskMMC.exe) - This is responsible talking to the background servicer and provide management feedback

Note:

If GtaskMMC.exe is run with /runlocal /server command line parameter, it will launch into the local native management console. Otherwise the /server flag alone will launch the web based console.




Fig. 1: GLADINET CLOUD ACCESS (GCA) SERVICE

By default the File Server Agent background windows service runs as a local system account.

Warning: Sometimes the LOCAL SYSTEM account doesn't have permission for the folders it wants to sync. In this case, the Log-on-as account for the Cloud Access Service (GladGroupSvc.exe) needs to be changed to a service account that has full control (read, write, delete, list) permission to the folder that it wants to sync.

In an Active Directory environment, this normally can be changed to a Domain Admin Service Account.

3.2 3.2 Cloud Server Console - Web View

CentreStack Cloud Server Console will launch automatically after the reboot using the Tenant Admin credentials that were used to install the software.

Warning: File Server Agent is tied to each Tenant, so the Tenant Admin's credential shall be used to link the File Server Agent to a specific Tenant.

The cluster admin is also the Tenant Admin for the very first Tenant in the CentreStack system so by default it is a Tenant Admin as well.

Note: File Server agent is managed at Tenant level (not per-user level, nor cluster-level either)

CentreStack Cloud Server Management Console Login:

CentreStack Cloud Server Management Console can also be launched from Windows Start Programs Menu:

Launch the Console from the Start Menu.





Fig. 2: GCA LOCAL SYSTEM ACCOUNT SERVICE



The image shows a dialog box titled "Configure ACME Systems Account". It has a blue header bar with a cloud icon on the left. The main area is white and contains three text input fields. The first field is labeled "User Name (Email):" and contains the text "acmeadmin@mailinator.com". The second field is labeled "Password:" and contains ten black dots. The third field is labeled "Access Point (http://myhost.com):" and contains the text "http://10.0.0.221". Below these fields is a blue hyperlink labeled "Proxy Setup". At the bottom right of the dialog are two buttons: "Ok" and "Cancel".

Configure ACME Systems Account

User Name (Email):
acmeadmin@mailinator.com

Password:
●●●●●●●●●●

Access Point (http://myhost.com):
http://10.0.0.221

[Proxy Setup](#)

Ok Cancel

Fig. 3: MANAGEMENT CONSOLE LOGIN




Fig. 4: LAUNCH THE CONSOLE

After launch, you see several options and tabs at the top of the view, Device Info is shown below.

The screenshot displays the ACME Systems Client Management Console. The top navigation bar includes the ACME Systems logo, the title 'Client Management Console', and a dropdown menu showing 'WIN-JCB9LU2673Q > DEVICE INFO'. Other tabs visible are 'MIGRATE CIFS SHARES' and 'MIGRATE USERS'. The 'Connected' status is indicated in green. The main content area is divided into four panels: 'Device Info' (left), 'Sync Status' (top right), 'Locked Files' (bottom left), and 'Attached Folders' (bottom right). The 'Device Info' panel lists various system details. The 'Sync Status' panel shows a large green checkmark and the message 'No sync task found.' The 'Locked Files' panel shows 'No locked file found.' The 'Attached Folders' panel shows a folder icon, the name 'TeamShareSA', the path 'C:\TeamShareSA', the label 'ATTACHED_FOLDER', and a refresh icon.

Device Info	
Device Owner	acmeadmin@mailinator.com
Allowed	<input checked="" type="checkbox"/>
Monitor Device Connect Status	<input type="checkbox"/>
Device Type	Server Agent
OS Type	Windows Server 2016 64bit
Device Client Version	9.7.2573.41582
Last Login Time	2Minutes ago
Sync Status	unknown
Cache Size	0 Bytes
Last Report Time	Less than 1 minute ago

Attached Folders	
TeamShareSA	C:\TeamShareSA ATTACHED_FOLDER

Fig. 5: CLIENT MANAGEMENT CONSOLE - DEVICE INFO

You can click on the left tab in the console to see more management items.

3.2.1 3.2.1 Device Info

The default web console view is the device information panel. It shows the basic device information such as device name, device operating system, device version and etc.

Monitor Device Connect Status - The device may get disconnected from the Internet for whatever reason, including but not limited to Internet outage, software crash, background service not running and etc. If the device is not connected to generate a healthy heart beat connection to the CentreStack server side software, this setting will generate an email alert if the device is not actively connected to the tenant account. When this alert is received, it needs to be investigated at high priority because it will lead to synchronization break-down.

3.2.2 3.2.2 CIFS Shares

CIFS (Common Internet File System) shares refers to Windows Network Shares that are available on the File Server Agent machine. CIFS shares or SMB (Server Message Block) shares are used interchangeably here.

You can start migrating file server network shares from the current machine to CentreStack.

Note: Migration means setup two-way synchronization between the local folder and the remote CentreStack Server.





Fig. 6: ACCESSING THE CONSOLE MENU



ACME Systems Client Management Console

WIN-JCB9LU2673Q > DEVICE INFO MIGRATE CIFS SHARES MIGRATE USERS Connected

Device Info


Device Owner	acmeadmin@mailinator.com
Allowed	<input checked="" type="checkbox"/>
Monitor Device Connect Status	<input type="checkbox"/>
Device Type	Server Agent
OS Type	Windows Server 2016 64bit
Device Client Version	9.7.2573.41582
Last Login Time	2Minutes ago
Sync Status	unknown
Cache Size	0 Bytes
Last Report Time	Less than 1 minute ago

task found.

hShareSA ATTACHED_FOLDER

No locked file found.

Fig. 7: CLIENT MANAGEMENT CONSOLE - DEVICE INFO



ACME Systems Client Management Console

WIN-JCB9LU2673Q > CIFS SHARES MIGRATE CIFS SHARES MIGRATE USERS Connected

REFRESH

	Name	Local Folder	
1	SA Share	C:\SA Share	Migrate
2	TeamShareSA	C:\TeamShareSA	
3	ADMIN\$	C:\Windows	Migrate

Fig. 8: CIFS SHARES

It is a hybrid cloud configuration started by default. Over time, you may want to stop the local folder and go cloud only. That is reserved for future if you select to do so. Out of the box it is setup as a two-way synchronization folder for each CIFS share selected.




Fig. 9: MIGRATE A SHARE

Note: The net result of migration is that you can access the files and folders from both the local file server and also the CentreStack side. Files changes on both side will synchronize to the other side. It is a hybrid local/cloud mode. Also when migration works on CIFS share (network share), optionally the local folder's NTFS permission can be replicated and synchronized to cloud side, while the local Active Directory users can be synchronized to cloud side.

3.2.2.1 Migrate

Clicking on the migrate link button will start the migration process on a specific network share. Normally when the File Server Agent and the CentreStack Server are on two completely different locations, the **“Direct Access”** option will not be shown. The **“Two Way Sync”** will be the only option.

3.2.3 3.2.3 Attached Folders

3.2.3.1 How to Attach a Folder

Attached folders, are folders on the local machine and can be synchronized to CentreStack and kept synchronized in a bi-directional way.

The Attached Folder section allows you to browse into the machine's file structure and pick a folder to synchronize. In the Console drop-down menu, select **“Attached Folders”**.

In the new view click the Attach Folder icon.

In the folder selection view (1), double click the drive (2) and navigate to the folder you wish to share. When you choose a folder, its path will appear in the Location field (3) and you should enter a name for your share in the Name field (4). Click **“ATTACH”** to complete the process.




Fig. 10: MIGRATION OF DATA AND PERMISSIONS




Fig. 11: ATTACHED FOLDERS




Fig. 12: ATTACH FOLDER BUTTON




Fig. 13: ATTACHING A FOLDER

3.2.3.2 Filter Button

Using the Filter Button (1), you can set some of your folders to be excluded from being synchronized. To accomplish this, after you click the **Filter** button, click the (+) button (2) and explore to a folder you wish to exclude. In this example, it is a sub-folder (3) of the **SA Share** folder.




Fig. 14: FILTER BUTTON

3.2.3.3 Diagnostic Button

The Diagnostic Button (2) can be used to “**Compare**” the cloud folder and the local network folder to determine if they are the same. This is important to make sure that the local folder has been completely mirrored to the cloud.




Fig. 15: DIAGNOSTIC BUTTON

3.2.3.4 Stop-Sync Button

The Stop-Sync Button can be used to stop the synchronization between the folder from the Server Agent and the attached folder in the cloud. This is something you might want to do when all the users are accessing the folder from the cloud and no longer need local network access to the original folder. After the stop-sync, the local file changes are local changes, not related to cloud; and vice-versa, the file changes in the cloud will not be related to the local files, they are just two separate independent entities.

Warning: Stop-Sync is different from detach a previously attached folder. When a folder is detached, not only it stop-sync, but also the cloud side folder will be hidden and subject to retention policy for purge in the near future. So if your use case is to continue to use the files and folders from the cloud side and cloud side only, you want to do a stop-sync instead of doing a detach-folder.




Fig. 16: STOP-SYNC BUTTON

Note: What is the difference between Import a CIFS Share and attach a folder to CentreStack?

First of all, both maintain bi-directional synchronization. The key difference is “Import CIFS Share” will also import folder permission to CentreStack, while Attached Folder only synchronize folders without synchronize permissions.

Under the hood, both are “**Attached Folders**”.

“Import CIFS Share” = “Attached Folder” + “Sync NTFS Permission”

3.2.3.5 Offline Folders

You can mark folders as offline. Offline folders will be pre-fetched to the local machine. Files changed remotely in the offline folders will also be pre-fetched to local machine.

To access this feature, click the “**Offline Folders**” icon (1). Then click the (+) icon (2) on the right side of the Offline Folders screen. In the explorer, navigate to the folder you wish to “Offline” and select it (3). Then click “**ENABLE OFFLINE ACCESS**” (4) to complete the process.

Note: When to use offline folder?

When you have files and folders that you use frequently, you want to keep them local to the local file server, you can enable offline folder.

Usually you use the offline folder for the gateway mode. When you use “Migrate CIFS share” or when you use “Attach Folder”, the files and folders by default are local so there is no need to enable offline folder for this use case since files are 100% off-line from attached folders.




Fig. 17: CHOOSING A FOLDER FOR OFFLINE ACCESS

3.2.3.6 Local File Lock

Local File Lock section will show locked files from the local file server.




Fig. 18: LOCKED FILES

3.2.3.7 Locked Files

Locked files section will show locked files from the CentreStack Server, and provides information about who owns the file that is locked. Information shown includes: File Owner, File Path, Locked From, Type and Locked Time.




Fig. 19: LOCKED FILES

3.2.3.8 Pending Check-ins

Pending check-ins will show files that are manually checked out from the local machine but haven't checked-in yet.




Fig. 20: PENDING CHECK-INS

3.2.4 3.2.4 Settings

Settings Manager section will show client settings that can be changed and managed from the web console.

3.2.5 3.2.5 Task Manager

Task Manager section will show the synchronization tasks that are running on the local machine. If there is a number on **“Pending Tasks”** or **“Failed Tasks”** you can click the text links next to those numbers to open a window that shows the tasks currently in progress. There are **“PAUSE”** and **“START”** buttons available on the left side of each of the task bars as well.

3.2.6 3.2.6 Migrate CIFS SHARES

Migrate CIFS Shares can be accessed from the Console menu or the **“MIGRATE CIFS SHARES”** text link. You can pick a network share on the local server and synchronize it to the cluster server. As explained above, this is how you migrate a folder and its NTFS permissions at the same time.

3.2.7 3.2.7 Migrate Users

Migrate users can import Active Directory users or local users to the CentreStack side as cloud users, while maintaining the same credentials as the local user.

3.3 3.3 Cloud Server Console - Native

You can launch the native management console from the program's installation folder. From the Command Prompt use the following command, `C:\Program Files\Gladinet\Cloud Server Agent>gtaskmmc /runlocal /server`




Fig. 21: SETTINGS MANAGER

ACME Systems Client Management Console

WIN-JCB9LU2673Q > TASK MANAGER > PENDING TASKS: MIGRATE CIFS SHARES MIGRATE USERS Connected

2 Task(s) found REFRESH

System Sync Task
PAUSE START System Sync Task Total Tasks: 4 Pending Tasks: 3 Failed Tasks: 0 Progress: 0 Next Run Time: 2018-07-26 14:05:14

System Sync Down Task
PAUSE START System Sync Down Task 6 14:05:15

3 Subtask(s)

Select All Deselect All Undo Selection Delete Selected Tasks

Task Name	Parameter1	
<input type="checkbox"/> Create Directory	/TeamShareSA/April	X Q
<input type="checkbox"/> Create Directory	/TeamShareSA/Joe	X Q
<input type="checkbox"/> Create Directory	/TeamShareSA/Tom	X Q

Fig. 22: TASK MANAGER

ACME Systems Client Management Console

WIN-JCB9LU2673Q > MIGRATE CIFS SHARES MIGRATE CIFS SHARES MIGRATE USERS Connected

REFRESH

Device Info CIFS Shares Local File Lock Attached Folders
Offline Folders Locked Files Pending Check-ins Settings
Task Manager

	Name	Local Folder	
1	SA Share	C:\SA Share	Migrate
2	TeamShareSA	C:\TeamShareSA	Q
3	ADMIN\$	C:\Windows	Migrate

Fig. 23: MIGRATE CIFS SHARES




Fig. 24: MIGRATE USERS

Once you have logged in the Native Console will open. This gives you local access to Server Agent settings.

3.3.1 3.3.1 Task Manager

Task Manager shows all the system related tasks.

You can also use the “Open My Cloud” link to access the Login Panel.

Each of the Task Manager sections below include a series of tabs that include the following:

‘Summary’

This tab shows a summary of all the “System Update Tasks”. It shows the “Task Type” where the type is the name of the task. It shows the ‘Status’ as “Pending” which means that the “System Update Task” is always looking for changes and is always in “Pending” state in case there are any updates that needs to occur.

Summary also shows the following:

‘Last Run Time’

This shows the time when the Server Agent software last detected the changes on the local file system and ran to update the files in the cloud.

‘Next Start Time’

This shows the time when the “Update Task” will run next. The counter increments every 15 seconds. The software will run the update tasks right away. You can also use the “Pause” option to stop the update Administrator can force the updates by clicking on “Start Now” option in which case the task from updating local changes to the cloud. “Delete Task” option allows to delete any tasks for which updates are not desired. “Refresh” will refresh all the counters on the ‘Summary’ tab.

‘Completed Subtasks’

This shows the number of upload subtasks that have been completed.




Fig. 25: LAUNCHING THE NATIVE MANAGEMENT CONSOLE




Fig. 26: NATIVE MANAGEMENT CONSOLE

‘Running Subtasks’

This shows how many subtasks are currently running. (See Tab for more info)

‘Pending Subtasks’


This shows the subtasks which are in pending state and waiting for their turn to get uploaded to the cloud.
(See Tab for more info)

‘Pending Retry Subtasks’

This shows the number of any tasks which are pending retry meaning for some reason the changes for some files were not uploaded to the cloud and hence they are in the **“Pending Retry Subtasks”** queue and as soon as their turn comes the changes for files in **“Pending Retry Subtasks”** will also be uploaded to the cloud. (See Tab for more info)

‘Trace’

This tab provides trace information about tasks. (See Tab for more info)



Time	Trace
2018-07-26 14:21:11 078	Process sub Task: MKCOL, /TeamShareSA/Tom
2018-07-26 14:21:11 016	Process sub Task: MKCOL, /TeamShareSA/Joe
2018-07-26 14:21:10 985	Process sub Task: MKCOL, /TeamShareSA/April
2018-07-26 14:20:58 760	[change]Detected file change, modified:Tom
2018-07-26 14:20:58 719	[change]Detected file change, added:Tom
2018-07-26 14:20:58 717	[change]Detected file change, modified:Joe
2018-07-26 14:20:58 664	[change]Detected file change, added:Joe
2018-07-26 14:20:58 645	[change]Detected file change, modified:April
2018-07-26 14:20:58 583	[change]Detected file change, added:April
2018-07-26 14:05:19 593	Process sub Task: CloudRenameFile, /TeamShareSA/forUsers/This is for Users and
2018-07-26 14:05:18 560	Rename changed file, target:forUsers\This is for Users and edited Admins.xlsx->fc
2018-07-26 14:05:18 529	Uploading changed file:forUsers\This is for Users and Admins.xlsx:226189592
2018-07-26 14:05:18 498	Process sub Task: CheckPoint, /TeamShareSA/forUsers/This is for Users and edite.

2 item(s) hidden, click [here](#) to show all items

Fig. 27: SYSTEM SYNC TASK - TRACE

The **“Trace”** tab in the **“System Sync Task”** lists all the uploading, downloading, and monitoring tasks.




Fig. 28: SYSTEM RELATED TASKS





Fig. 29: SYSTEM SYNC TASK

3.3.1.1 System Related Tasks

3.3.1.2 System Sync Task

It is the master sync task and its job is to keep an eye on both local file changes and file changes that are done in the cloud. This is the task which triggers the “**System Update Task**” or the “**System Sync Down Task**”.

3.3.1.3 System Sync Down Task



The screenshot displays the 'System Sync Down Task' interface. At the top, there is a title bar with a logo and a close button. Below the title bar is a navigation bar with tabs: 'Summary' (selected), 'Running', 'Pending', 'Pending Retry', and 'Trace'. The main content area shows the following details:

- Task Type:** System Sync Down Task
- Status:** Pending
- Pending Subtasks:**
- Completed Subtasks:**
- Pending Retry Subtasks:**
- Running Subtasks:** 0
- Last Run Time:** 2018-07-25 14:15:12
- Next Start Time:** 2018-07-26 16:11:28

At the bottom of the interface, there is a control bar with four buttons: 'Start Now' (green play icon), 'Pause' (yellow pause icon), 'Delete Task' (red X icon), and 'Refresh' (blue refresh icon). Below the control bar, a message states: '2 item(s) hidden, click [here](#) to show all items'.

Fig. 30: SYSTEM SYNC DOWN TASK

It performs the exact same tasks as the “**System Update Task**” but its job is to ensure that the changes that are done to the files in the cloud are automatically synced down to the file server. The “**System Update Task**” and the “**System Sync Down Task**” are what provides the mirroring or two-way sync between the local files on the cloud server and the files in the cloud.

3.3.1.4 System Update Task

It shows all system related update tasks. Server Agent software checks the local file system every 15 seconds and when it notices the changes to the files, the changed files will be added to the upload queue. The real upload time depends on how big the upload queue is and if there is only one file with the changes, the changes to the file will be uploaded to the cloud in 15 seconds.




Fig. 31: SYSTEM UPDATE TASK

3.3.1.5 Edit Account Information




Fig. 32: EDIT ACCOUNT INFORMATION

This link at the bottom allows you to **Login with different credentials** to launch the Cloud Server Console and perform management related tasks.

3.3.2 3.3.2 File Server

“**File Server**” shows all the data that have been uploaded to the cloud and the files and folder structure. It lists folder structure which includes sub-folders as well. The local folders that are attached either from the file server or a user’s machine have the machine name in parenthesis.

An Administrator can create a new sub-folder below selected node or can attach additional local folders using the “**Attach Local Folder**” option under “**Actions**”. Attaching a local folder to CentreStack Cloud using the “**Attach Local Folder**” option allows immediate access to the local content from anywhere using any device. “**Attached Local Folder**” will be synchronized upwards to the cloud first and also the changes in the cloud will be sync down to the local file server.

Administrator can also highlight an existing cloud folder and create new sub-folders underneath that highlighted folder.

Note: The two-way synchronization feature of the “**Attach Local Folder**” only applies to local folders such as those on the C: drive, D: drive and local hard drives in general. It won’t work for network share. The two-way




Fig. 33: FILE SERVER

synchronization depends on the local file system's event change notification about files and folders. These changes will be detected and synchronization will happen based on the changes.

An administrator can also manage the folder using Web Portal by using the **“Manage”** option. This will allow an admin to convert any folders that have been attached to the cloud or are in the cloud to convert them into **“Team Folders”** for collaboration etc. Highlight the folder and select **“Manage”** under **“Actions”**.




Fig. 34: FILE SERVER - MANAGE FOLDER IN WEB PORTAL

In the Manage Folder view, you must add collaborators to make this a team folder. The pop-up lets you choose a source for your users/groups; either Existing User/Group or AD.

Once you have added your users/groups, click the Disk icon to save your changes. Click the Settings tab to modify settings for this share.

In the Settings tab view, you can modify the settings for this share including: Basic Settings, Permissions, Secure Data Room, IP White List and Quota and Retention Policy. Under the (+) Settings sub-menu you have access to: Disable further sharing, Create CIFS Share and Disable Offline Access options.

That diversion shows you how you can create, access and modify folders and settings from within the Web Portal of CentreStack. Now we return back to the File Server section of the Server Console in Server Agent. **“Enable Background Prefetch” (1)** makes the contents of the selected folder available offline.

“Delete” does not remove the content of the folder from local storage; however, it does detach the selected folder and its contents from the cloud. If you go to the Web Portal and re-create a folder with exactly the same name (including the machine's name and the parenthesis), the folder can be shown with a cloud-only context without any local machine relationship.




Fig. 35: ADDING COLLABORATION




Fig. 36: ACCESS TEAM FOLDER SETTINGS




Fig. 37: TEAM FOLDER SETTINGS




Fig. 38: FOLDER ACTIONS




Fig. 39: FOLDER ACTIONS

“**Attach a Folder to Backup**” (see above) allows an administrator to attach and two-way synchronize a local folder to the cloud. The default view shows all the “Attached-Folders” on the local machine that are attached to the cloud. To add a folder click the browse icon (...) and search for a folder to sync to the cloud.




Fig. 40: ATTACH LOCAL FOLDER

Once a folder is attached, you can take advantage of one of the Folder Actions “**Manage**” that allows you to quickly open a Web Portal to edit Sharing and Collaboration settings for the folder.

3.3.3 3.3.3 Attach/Backup

Clicking the Attach/Backup button shows all of the folders currently attached.

By clicking the double-down-arrow icon on the right of each share you can see the details of the folder and if the folder is linked to a local folder you will see “**Link to local**”. If it is already linked you will see “**Stop Sync**”. As shown below, you can also **Detach** the folder in this location.




Fig. 41: MANAGE FOLDER FROM WEB PORTAL




Fig. 42: SELECT SHARING AND COLLABORATION




Fig. 43: ALL FOLDERS WITHIN ADMIN'S ROOT FOLDER




Fig. 44: ATTACH/BACKUP SETTINGS

3.3.3.1 Link to Local Folder

You can take a folder that is in the cloud and sync it down to a local folder and then maintain two-way synchronization.

3.3.3.2 Stop Sync

You can break the two-way sync between a local folder and a folder in the cloud. After stop sync, the two sides continue to exist but there is no relationship between them any longer.

3.3.3.3 Detach

Detach is the reverse of Attach. Attach means attach a local folder to the cloud under version control. Detach means remove it from the version control. Detach is an operation detaching the cloud side of the folder from version control. After detach, the local folder (if it is related to a local folder) is not affected at all. However, the folder in the cloud will disappear.

Note: If you want the cloud side of the folder to reappear, you can use “Show Deleted” in the Web Portal to show the deleted folder and bring it back. Or you can create a same name folder from scratch to inherit the folder back.

3.3.4 3.3.4 Audit Trace

Audit trace shows the history of all the tasks that have taken place. Administrators can query the “**Audit Trace**” to see the history of uploads, downloads, changes, and monitoring on the files in the cloud. You can also filter the tasks you would like to query by using the “**Only Show Traces Containing**” field (1).

As an administrator you can also specify the times that you would like to run the query for (2). Additionally, you can specify the amount of traces you would like to query (3) where “0” means unlimited traces.

3.3.5 3.3.5 Settings Manager

Server Agent administrators can customize and configure many settings at the Server Console level by modifying the contents of the Settings Manager section.

From here you can also access the “**Offline Folders**” tab.

3.3.5.1 Offline Folders

This section lists all the cloud folders which have been enabled for “**Offline Access**”, meaning users who have access to offline folders can access and edit the contents of such folders even when they are not online. All the changes done to files in offline folders will be automatically synced as soon as the users come back online.

“**Add New Offline Folder**” You can click this link to configure a folder as an Offline Folder.

ACME Systems Server Console

Time	Trace
2018-07-27 11:17:06 916	[FileSvr]SetTeamShares:TeamShareSA,true
2018-07-27 11:17:06 875	[FileSvr]SetTeamShares:teamFolder,false
2018-07-27 11:16:53 883	[FileSvr]SetTeamShares:TeamShareSA,true
2018-07-27 11:16:53 836	[FileSvr]SetTeamShares:teamFolder,false
2018-07-27 11:16:51 932	[mon]root monitor:C:\TeamShareSA, enter loop
2018-07-27 11:16:51 932	[mon]Scan perm:C:\TeamShareSA, enter loop
2018-07-27 11:16:51 837	Update folder permission:/TeamShareSA, C:\TeamShareSAS-1-5-18Systemtrueuetru...
2018-07-27 11:16:51 837	Update folder permission:/TeamShareSA, C:\TeamShareSAS-1-5-18Systemtrueuetru...
2018-07-27 11:16:51 806	[mon]Starting monitor:C:\TeamShareSA, enter loop
2018-07-27 11:16:51 806	[mon]begin scan tree:C:\TeamShareSA
2018-07-27 11:16:51 806	Update folder from root scan:root, gsync_TeamShareSA
2018-07-27 11:16:51 791	[mon]Starting monitor:C:\TeamShareSA

Audit Trace Query Interface:

- ☒ Only Show Traces Containing **1** teamshare
- ☐ Only Show Traces Between **2** 7/27/2018 - 7/27/2018
- Maximum Traces to Show (0-Unlimited) **3** 200
- [Query](#) [Copy To Clipboard](#)
- [Open My Cloud](#) [About ACME Systems Server Agent](#)

Team Edition Version: 9.7.5645.41666 Connected Upload: 0.000 KB/S Download: 0.069 KB/S

Fig. 45: AUDIT TRACE QUERY




Fig. 46: OFFLINE FOLDERS

3.3.5.2 Settings Tab

3.3.5.3 Bandwidth Control

As an administrator you have full control over how much bandwidth should be consumed for uploading contents to the cloud and also for downloading contents from the cloud. You can also control how many consequent uploads and downloads are allowed at any one time.




Fig. 47: SETTINGS MANAGER - BANDWIDTH CONTROL

“Download Bandwidth Limit (KB/s, 0-Unlimited)” Default is **“0”**. This setting is applied to the local machine (Server Agent). Usually something > 100KB/s is good. If it is too small, it can negatively affect performance and usability.

“Upload Bandwidth Limit (KB/s, 0-Unlimited)” Default is **“0”**. This setting is applied to the local machine (Server Agent). Usually something > 100KB/s is good.

“Number of Upload/Download Threads” Default is **“5”**. Set this from 5-10 in general. In some case, if you set it to a very big number such as 20, it may negatively affect performance. For example, if you are using Amazon S3 and Amazon S3 or other Cloud services may have per-client thread policy so if you have too many concurrent upload/download, it may get regulated outside of the Server Agent.

3.3.5.4 Cache

You can change the location of Cache (for files downloaded locally from cloud). You can also set the cache size.




Fig. 48: SETTINGS MANAGER - CACHE SETTINGS




Fig. 49: SETTINGS MANAGER - SYNC CONTROL

3.3.5.5 Sync Control

“Throttle Sync” Default is **“False”**. If you set this flag to **“True”** it will stop and start the sync depending on the available bandwidth.

“Sync Throttled Upload Bandwidth (KB/s, 0-Unlimited)” Default is **“0”**. Where **“0”** means unlimited bandwidth is available for upload sync.

“Sync Throttled Download Bandwidth (KB/s, 0-Unlimited)” Default is **“0”**. Where **“0”** means unlimited bandwidth is available for download sync.

“Full Speed Sync Stop Hour (default 7:00)” Default is **“7”**. Use this setting to set when full sync stops, to prevent bogging down your system during business hours.

“Full Speed Sync Start Hour (default 20:00)” Default is **“20”**. Use this setting to set when full sync starts, to prevent bogging down your system during business hours.

“Scan local files and sync up to cloud as necessary” Default is **“False”**. Set this to **“True”** if you want the agent to scan the local file system and make sure that everything which is not synced to the cloud is truly synced.

“Scan cloud files and sync up to local as necessary” Default is **“False”**. Set this to **“True”** if you want the agent to scan the cloud and make sure that everything which is not synced to the local file system is truly synced.

“Optimize Sync Down Notification” Default is **“False”**. If you want to see sync down notifications, then set this to **“True”**.

“Ignore file dummy change notification” Default is **“False”**. If you don’t want to see dummy file change notifications, then set this to **“True”**.

“Enable sync folder permission in attached folder” Default is **“False”**.

3.3.5.6 Advanced

Administrator can locate the cache directory under **“Advanced”** option in settings. Using the **“Cache Size Limit (MB)”** field can specify the size limit for the cache file.

“Do not Mount Drive” Default is **“False”**. When you set this to **“True”** local drive on the Server Agent is unmounted.

“Domain Controller IP or Hostname” This setting is empty by default.

“Enable In-place Open Zip File” Default is **“False”**. This field enables in-place editing on files which are in zipped folders in the cloud. You can also specify the maximum size for zipped files that are allowed for In-place editing.

“Max Size of Zip File Allowed to Open Inplace” This is **“20”** by default. Use this field to set the maximum size of Zip Files that can be opened inside the Cloud Drive in MB.

“Ignore Settings in Group Policy” Default is **“False”**. When you set this flag to **“True”**, the configured settings in the Web Portal will be ignored and the settings configured here under **Settings > Advanced** will take precedence.

“Interval to Keep Group Relationship in Cache (Min)” The default is **“60”** minutes. This field is a performance optimization setting. The Server Agent will check the remote requests against the ACL (Access Control) set on the local files. Most of the times it involves Active Directory or NT domain group membership checking. The group membership checking is a CPU intensive work so the result is cached to improve performance. This controls how long the result will be cached. If users are not changing group frequently, you can set the interval to a long period of time.

“Purge File Sys DB Upon Start” The default is **“False”**. If you change this setting to **True**, upon startup the client will purge the cached cloud storage state file. This allows the client to rebuild the database as if it is being started for the first time.

“Upload Hidden Files” The default is **“False”**. If this flag is set to **“True”** then hidden files will also be uploaded to the cloud.




Fig. 50: SETTINGS MANAGER - ADVANCED

“Upload System Files” The default is **“False”**. If this flag when set to **“True”** then system files will also be uploaded to the cloud.

3.3.5.7 Trace

The audit trace log can grow exponentially if not kept under control. As an administrator you can specify the number of days to keep the audit trace. **“Days of Audit Trace to Keep”** setting is the field to specify the duration to keep the trace for.

Trace Level when set to **“0”** which is the default does not collect any traces meaning it is disabled.

Trace Level 1 – error will collect all the error traces.

Trace Level 2 – warning will collect warning traces along with errors.

Trace Level 3 – info will collect errors, warnings, as well as info traces.

Trace Level 100 – verbose helps developers to collect detailed traces which helps them when debugging issues.

Note: When it is necessary to collect DebugView trace for debugging purpose, the Trace Level typically is set to 101.




Fig. 51: SETTINGS MANAGER - TRACE

4.1 4.1 Migration Users

With the Server Agent installed, it can be used to migrate Active Directory users to CentreStack users.

The process can be started from the Tenant Administrator Web Portal.

4.2 4.2 Migrate File Server Network or CIFS Share to CentreStack

With the Server Agent installed, it can be used to migrate local folder (which is published as network share) to CentreStack as a team folder, and at the same time, migrate Active Directory users to CentreStack users.

The steps can be started from the migration wizard in the Tenant Admin's Web Portal.

4.3 4.3 Conclusion

Businesses are looking for ways to access file server contents over the Internet. They are looking for technologies which will allow them to migrate the data residing on On-Premise file servers to the cloud and provide a unified namespace across all distributed file servers. They are also looking for ways to give remote users easy and secure access to their file server without disrupting the existing work flow in the company.

CentreStack Cloud Server (File Server Agent) combines the strengths of cloud storage technology and traditional file server to enable data access from the cloud by enabling sync, share, and collaboration on that data.

CHAPTER 5

Indices and tables

- `genindex`
- `modindex`
- `search`